# PaceTrainer App User Manual

### **Table of Contents**

Purpose of PaceTrainer App
Starting the PaceTrainer App
- Page explanation
- Required values/fields
- Dropdown menu
<u>Using PaceTrainer App</u> 5
- Connecting with Bluetooth
- Pick your profile
- Choose a theme
- Select Language
Support6
- Contact the developers
- Send us an email

## Purpose of PaceTrainer App

Idea: Swimmers possess no visualization within the water to determine their speed. Our idea is to create an RBG LED racing light that allows swimmers to control and improve their time. This device increases competitive performance by racing alongside the swimmer.

Purpose: The purpose of the PaceTrainer App is to extend flexibility via your mobile device or tablet.

### Starting the PaceTrainer App

<u>Prerequisites:</u> Phone Bluetooth must be turned on, along with having the Arduino device ready to pair. No other pairable devices should be turned on within the vicinity of the device.

**Bluetooth:** Before entering any of the required fields or selecting a workout, please connect your Bluetooth device to the Arduino. This is required because the data entered will be transmitted to the Arduino via Bluetooth serial. If the Bluetooth refuses to connect, please send us an email via the Support section.

<u>Page Explanation:</u> [Main Page] The PaceTrainer App is divided into four sections. Opening the app, the main page consists of fields that allow you to choose your workout preferences.

=		Field	Definition
Pace Trainer			Enter how many times
Repetitions		Repetitions	you wish to repeat the workout:
			1 - 99
1			Set your time pace
		Pace	mm:ss:ff
Pace			[minutes : seconds:
			fractions of seconds]
			Set your time interval
Interval		Interval	mm:ss:ff
			[minutes : seconds:
			fractions of seconds]
Pool Length			Choose the length of
05		Pool Length	your pool:
25y	0		25 yards or 25 meters
		Distance of workout:	
Distance		Distance	Dropdown from
			25 – 1650
	0		[meters/yards
			depending on Pool
Start Color			length]
	0	G G. 1	Choose the light starting
		Start Color	color at the beginning of
			workout:
Main Page		Race Color	Red, Blue, Green
			Choose the light racing
			color for workout:
			Red, Blue, Green


**Page Explanation:** [Bluetooth] Once your devices are in pairing mode, press the connect

button pictured in the Start/Stop/Store screen shot. You will see the message "Connected to <u>macAddress</u>" if your Bluetooth device is properly connected.

<u>Page Explanation:</u> [Start/Stop/Store Buttons] Once all your preferences are entered, you have ability to either store the workout, start the workout, or stop the workout. NOTE all fields must be entered for START to work.



Bluetooth



Start/Stop/Store



Settings


<u>Page Explanation:</u> [Dropdown button] There is a dropdown bar for easy access to your workout profile and settings page.

<u>Page Explanation:</u> [Settings] Change the language, choose a Light or dark mode theme, or choose to delete all your workouts.

Page Explanation: [Breakout Page] From the main page, you can swipe right to choose your breakout distance. The breakout distance is the distance you emerge out of the water after diving in. You will have to swipe left to go back to main page.




Breakout



Dropdown

<u>Page Explanation:</u> [User Profile] Using the dropdown button, you can select "Workout Profiles" to choose previous workouts. Once, selected, they will automatically enter the field data. You may go back to the main page by using the dropdown button or the "Go Back" button at the bottom of the page.



User Profile

### Using the PaceTrainer App

<u>Connect with Bluetooth:</u> As stated in the <u>Starting the PaceTrainer App</u> you must first connect to the Arduino device via Bluetooth. Make sure both devices are suitable for pairing and simply press the "Connect" button via the main page.

<u>Select Your Profile:</u> Once your phone is connected to Bluetooth, you can either select a previously ran workout or enter new distances for the required fields. Once all your preferences are chosen, press the START button at the bottom of the main page. This will send your personalized workout to the PaceTrainer device.

<u>Adjusting/Deleting Your Workout:</u> If you feel the data you entered is too slow/fast, you can correct your preferences via the main page. The PaceTrainer App allows users to delete their workouts in the SETTINGS page via dropdown button.

<u>Adjusting Your Theme:</u> Currently, the PaceTrainer App has two themes – light and dark. Head to the SETTINGS page to change back and forth!

<u>Adjusting Your Language:</u> Currently, the PaceTrainer App has one other language – Spanish. You can visit the SETTINGS page to change the language.

## PaceTrainer App Support

Blake Morrell Matthew Felsen Emilio Miles

bmorrell@ku.edu emiles3@ku.edu emiles3@ku.edu

Note to Users. We hope to implement a time storage option with future releases. Our goal is to encourage competitive competition among schools and athletes. Thank you for downloading!